

# Quilt Designer II

## Update 1.52

A new program update for Quilt Designer II och Designer II, named version 1.52, is now available. The program contains the following improvements:

### Open Toe Free Motion Spring Foot can now be used

Set the machine for Sensor Q-foot. Deselect Stitch Width Safety (SET 4) to allow wide stitches when using the new Open Toe Free Motion Spring Foot (optional accessory 413 03 76-45).

### Sensor Q-foot setting now available for all stitches

Previously only stitches from the V-menu could be used with the Sensor Q-foot. Now all stitches can be used.

### Update Application

The update application now works with both 3D and 4D Embroidery system drivers.

