

Designer I Update 2.2

The Designer I update, version 2.2, is common for Designer I USB and Designer I. Two separate update files are available on the Husqvarna Viking homepage, one for a USB memory and one for a floppy disk.

The new Designer I program contains the following improvements.

Open Toe Free Motion Spring Foot can now be used

Set the machine for Sensor Q-foot. Deselect Stitch Width Safety to allow wide stitches when using the new Open Toe Free Motion Spring Foot (optional accessory 413 03 76-45).

Sensor Q-foot setting now available on all stitches

Previously only V-menu stitches could be used with the Sensor Q-foot. Now all menus can be used.

