



autodigitizing

Getting Started

Lettering 2: Single Line, On Screen Placement

1. Open autodigitizing, or click New Design  to get a blank screen if autodigitizing is already open.
2. Set Edit/Display Preferences/Hoop and select a small/medium sided hoop (approximately 100 by 100 mm).
3. Click on the  Insert TrueType Font icon on the toolbar. The Insert Text dialogue box will display.
4. In the Characters box, type "Smile"
5. Click+hold and drag to highlight the letters.
6. Set Style to Garamond, Size to 17.78, Baseline to Line with a check in Onscreen Input, Check by Bold and Italic, select a new color, set Alignment left, set Spacing 0.00.
7. Click OK to accept the settings.
8. The mouse cursor will change to a circle with crosshairs.
9. Left click in the left side of the screen, just inside the edge of the hoop outline, to place the beginning of the baseline.
10. Left click again at the right side of the hoop to place the ending of the line.
11. If you place the two points across from each other in line horizontally, your lettering will have a level baseline.
12. If you place one point higher and the other lower, the baseline will tilt at the angle created between the two points.
13. The lettering will appear automatically after the second click, with the black select boxes and in Outline Mode.
14. Generate and Save as Smile in ASD format, then Export as Smile in the correct format for your machine.

